

# *Halfile Print to Setup with Printers4*

---

This document will assist you in the installation of Print to halfile with Version 3.0 and 4.0 of halfile For Windows.

## **Notes for Printers4 Print to installation:**

- You can use the “new” PRINTERS4 halFILE printer on all workstations whether they are 32-bit or 64-bit.
- Printers4 Print To version is a requirement on 64 Bit PC’s.
- Any existing halFILE printers will need to be deleted and configured again.
- A mix of old versions of HF printer and the new Printers4 will not function correctly on the network.

## **Installation Procedure**

1. Login as an administrator to the PC in order to do the installation and UAC should be in the turned OFF for Windows 7 PCs.
2. Name the existing HALFILE\INSTALL\PRINTERS\ folder to..\PRINTERS\_OLD and make a new HALFILE\INSTALL\PRINTERS folder.
3. Download PRINTERS4.EXE from <http://download.halfile.com> and copy it to HALFILE\INSTALL\PRINTERS folder and extract the contents to that same folder.
4. Download HALPRN32.V40 from download.halfile.com and copy it to HALFILE\ program directory. Name the existing HALPRN32.EXE to .OLD and put the new downloaded file in place as HALPRN32.EXE.
5. Copy HALPRN32.EXE to HALFILE\DELIVER\ folder replacing the old file.
6. At each workstation copy HALPRN32.EXE to local C:\HALFILE\ folder overwriting the old one.
7. From Start\Run (on Windows XP) or Start\Search Windows Programs and files (Windows 7) Type in path to halfile directory and add “halprn32.exe CONFIG” on the end. For example:  
“H:\halfile\HALPRN32.exe CONFIG”
  - a. On the “Printers” tab, click the “Delete all Printers” button.
  - b. Then click NEW and INSTALL.